

BRUHN
NEWTECH
LIFE SAVING SOFTWARE SOLUTIONS

How to set up own Mail Box for Mail Media (MAPI)



www.bruhn-newtech.com

Communication – Own Mail Box - MAPI

- Click on Menu: File
- Click on Properties
- Click on Communication


Lan Media is default

LAN media is default and is shown immediately

However, you want to use the computer e-mail (MAPI).

(Note: You can use both e-mail and LAN if both media are available)

- To select MAPI, click on Add





Communication – Own Mail Box - MAPI

1. The MAPI media will be show
2. Click OK
3. Select MAPI profile e.g. Office365 (or EXCHANGE or Outlook etc.)

If nothing is available, your computer does not have a MAPI account and mail media cannot be used.

4. Click on Scan inbox for me....



to secure CBRN messages received before CBRN-Analysis was opened will be copied into the program




Communication – Own Mail Box - MAPI

The MAPI media is now selected

1. Click OK
2. Click OK



Communication – Own Mail Box - MAPI




You will now be asked to **restart the program** (not the computer) before the setup is activated.

Click OK and restart CBRN-Analysis

Communication – Own Mail Box - LAN

If this message (or a similar message) shows when the program start up explaining that your communication media is NOT available

The media selected as your mail box is not available e.g. because of wrong setting or (most likely) you have no connection to your e-mail media e.g. the mail program may not be started



You will not be able to communicate until this has been fixed

Note that if the e-mail is not working - this cannot be corrected by CBRN-Analysis, it is an external error

After the media has been restored you must restart the program to make your communication work again